

# Hardware key (HASP HL, SD and SDX) Upgrade Procedure

This document presents the hardware key upgrade procedure using C2R / R2C files.

First generate a **C2R** (Client to Reseller) file and send that to TEKLYNX, as indicated in **Part 1**. Then use the **R2C** (Reseller to Client) file you receive to upgrade the key, as indicated in **Part 2**.

# Part 1 – Generate a C2R file to attach it to your order

#### Generate a C2R file

1. Connect the hardware key to your PC.

Note: Ensure you have only one key connected (parallel & USB ports) \*\*\*.

- 2. Launch the Key Upgrade tool (Upgrade.exe) from:
  - The Installation folder of the product.
  - From Windows 8 onwards, via the Windows search tool. To access the search tool, press **Win** [Windows key] + **S** on your keyboard. When the menu appears, enter **Upgrade.exe**.

The latest version of the **Key Upgrade** tool is available via this link: <u>https://www.teklynx.com/-/media/Files/Updates/HASP/upgrade.ashx</u>

	&	Key Up	ograde	+		×
Check that displayed key version is the one which you want to upgrade.	Serial Number	Once the new version of the product is in licenses the product. The key must be co	stalled, use this tool to upgr nnected to this computer. Key HASP HL - USB1	ade the h	ardware key that	
*** If you have connected the wrong key: - click <b>Close</b> , - connect the correct key - restart the Upgrade.exe	Product [Product Name Choose this upgrade. Client to Re Choose this to your rese	2] Client option to upgrade your hardware key licer seller option to get an image of your hardware k lier.	nce using the R2C file that y key license. This will general	iou receiv te a C2R I	red with your file that can be ser	nt
	English	•	Next >		Close	



- 3. Select the desired display language from the list.
- 4. Select Client to Reseller.
- 5. Click Next.

4	Key Upgr	ade	+	- 🗆 🗙	
Once the new version of the product is installed, use this tool to upgrade the hardware key that licenses the product. The key must be connected to this computer.					
Serial Number		<ey< td=""><td></td><td></td></ey<>			
[Serial Number]	H	ASP HL - USB1			
⊢ Product					
[Product Name]					
Select the file with the extension C2R in which your hardware key information will be stored. File name:					
[Serial Number].C2R					
	< Previous	Next >		Close	

6. Click the button. The **Save As** dialog box appears.

The **Save As** dialog box lets you specify the drive and the folder where you want to save your **C2R** file.

**Note**: for accurate follow-up, we suggest you name the C2R file with the **serial number** of the product concerned by the key upgrade.

7. Click Next.

A message will inform you that you have successfully generated a C2R file.



3	Кеу Up	grade	<b>+</b>		×
Once the new version of the product is installed, use this tool to upgrade the hardware key that licenses the product. The key must be connected to this computer.					
Serial Number –		Key			
[Serial Numb	er]	HASP HL - USB1			
[Serial Number]     HASP HL - USB1   Product [Product Name]       The process was successfully completed.					
	< <u>P</u> revious			<u>C</u> lose	

#### Send an e-mail to TEKLYNX

Create an upgrade request e-mail containing at least:

- ✓ The product name and current version
- ✓ The upgrade required
- ✓ The C2R file you generated
- ✓ The **serial number** of your product

To ensure your request is processed efficiently, please send your email in English or in French ONLY, to your usual contact address for orders:

customer\_care@teklynx.fr for Western Europe, Middle East and Africa info\_gr@teklynx-int.com for Central, Eastern and Northern Europe customerservice@teklynx.asia for Asia and Pacific

After receipt of your e-mail, TEKLYNX will generate an **R2C** file and will send this to you by return e-mail.

When you have received the **R2C** file, you must complete **Part 2** of this procedure to upgrade your hardware key.



# Part 2 – Upgrade the hardware key

1. Connect the hardware key (which corresponds to your upgrade) to your PC.

Note: Ensure you have only one key connected (parallel & USB ports) \*\*\*.

- 2. Launch the **Key Upgrade** tool (Upgrade.exe) from:
  - The Installation folder of the product.
  - From Windows 8 onwards, via the Windows search tool. To access the search tool, press **Win** [Windows key] + **S** on your keyboard. When the menu appears, enter **Upgrade.exe**.

The latest version of the **Key Upgrade** tool is available via this link: <u>https://www.teklynx.com/-/media/Files/Updates/HASP/upgrade.ashx</u>

Check that displayed key version is the one which you want to upgrade.

\*\*\* If you have connected the wrong key:

- click Close,
- connect the correct key
- restart the Upgrade.exe

ا &	Key Upgrade	<b>+</b>		×	
Once the new version of the product is installed, use this tool to upgrade the hardware key that licenses the product. The key must be connected to this computer.					
Serial Number	Key-				
[Serial Number]	HASP HL - USB1				
Product [Product Name]					
Reseller to Client Choose this option to upgrade your hardware key licence using the R2C file that you received with your upgrade.					
Client to Reseller C Choose this option to get an image of your hardware key license. This will generate a C2R file that can be sent to your reseller.					
English	Next >		Close		

- 3. Select the desired display language from the list.
- 4. Select Reseller to Client.
- 5. Click Next.



6. Click the button and select the file with the extension **R2C** that you received.

å	Key Upgr	ade	<b>+</b>		×	
Once the new version of the product is installed, use this tool to upgrade the hardware key that licenses the product. The key must be connected to this computer.						
Serial Number	K	ey				
[Serial Number] HASP HL - USB1						
Product						
[Product Name]						
Select the file with the extension R2C that you received with your upgrade. Then click on 'Next'. File name:						
ji [rile namej.k20						
	< Previous	Next >		Close		

# 7. Click Next

A message will inform you that the product has been upgraded.

# 8. Click Close