TEKLYNX® CENTRAL



INSTALLATION GUIDE



TEKLYNX CENTRAL Installation Guide

The information in this manual is not binding and may be modified without prior notice.

Supply of the software described in this manual is subject to a user license. The software may not be used, copied or reproduced on any medium whatsoever, except in accordance with this license.

No portion of this manual may be copied, reproduced or transmitted by any means whatsoever, for purposes other than the personal use of the buyer, unless written permission is obtained from Teklynx Newco SAS.

© 2015 Teklynx Newco SAS. All rights reserved.

TEKLYNX and its products are trademarks or registered trademarks of Teklynx Newco SAS. All other brands and product names are the trademarks of their respective owners.

Table of Contents

Chapter 1: Getting Started	1-1
About this Manual. Product Components. System and Server Requirements. Other Documentation Resources	1-1 1-2
Chapter 2: Installation	2-1
Welcome!	2-1
Chapter 3: Using the Command Center	3-1
The Command Center Managing Software Maintenance Agreements Managing Licenses Using the Label Designer Using the Label Manager Using the Print Manager Using the Printing Interface	
Using the Workstation Install Module	3-25

Getting Started Chapter 1-1

CHAPTER 1

Getting Started

About this Manual

This manual is designed to provide you with the basic information you need to install, configure, and use TEKLYNX CENTRAL.

Typographic Conventions

This manual uses the following conventions to distinguish between different types of information:

- Terms taken from the interface itself, such as menu names, commands and button names appear in **bold**.
- Keys appear in uppercase, as in the following example:
 "Press the SHIFT key."
- · Numbered lists indicate a procedure to follow.
- The sequence for selecting a command from a menu will be described, but a button is also available for many functions.
- Angle brackets <> indicate system setup information that must be entered by keyboard. Enter only the information, not the brackets

Product Components

Your software is packaged with the following components:

- DVD
- This documentation

Chapter 1-2 Installation Guide

System and Server Requirements

Processor	Minimum: 2 GHz or faster			
Operating System	 Windows Server 2008 R2 x64 Windows Server 2008 SP2 x32/x64 Windows Server 2012/2012 R2 x64 			
Memory	1 GB of free RAM			
Hard Disk Space	Minimum 1.5 GB of free disk space			
Supporting Software	On the server: Microsoft Internet Information Services (IIS) 7.0 or higher Microsoft SQL Server 2008/2008R2/2012, Oracle 11 .NET Framework 3.5 SP1 (Server and Client), 4.5.2 (Server) ASP .NET 4.0 On the print client: Microsoft Internet Explorer 10, Mozilla Firefox 23.0, Google Chrome 29.0 or later On the label designer client: Microsoft Internet Explorer 10, Mozilla Firefox 35.0, Google Chrome 40.0 or later .NET Framework 3.5 SP1 Microsoft Data Access Components (MDAC) 2.8 or later Adobe Acrobat Reader X or later			
Video Card	DirectX 9.0 minimum			
Additional Requirements	Administrator rights to the computer used during installation			

Other Documentation Resources

Product DVD

In addition to any printed documentation that may be included with your product, you can find all available TEKLYNX CENTRAL documentation in PDF format on the product DVD.

Getting Started Chapter 1-3

> The PDF documents can be viewed in Adobe Acrobat Reader and printed for easy reference.

To access the TEKLYNX CENTRAL documentation on the DVD, click the Installation Guide button available on the DVD's opening screen.

You can also download product documentation at www.teklynx.com.

Other Product

Supplementary manuals for CODESOFT, LABEL ARCHIVE, **Documentation** SENTINEL, and the Printing Interface are also included on the DVD. For more detailed instructions on these products, refer to the corresponding product documentation.

> User and administration manuals for these applications are also available online at www.teklynx.com.

Installation Chapter 2-1

CHAPTER 2

Installation

Welcome!

Thank you for purchasing TEKLYNX CENTRAL. This installation guide contains information on how to install and configure TEKLYNX CENTRAL, in addition to using the Command Center to interact with CODESOFT, LABEL ARCHIVE, SENTINEL, and the Printing Interface.

About TEKLYNX CENTRAL

TEKLYNX CENTRAL manages enterprise labeling users, licenses, and installation within one interface. The Command Center coordinates TEKLYNX' proven label design, printing, security, and tracing applications to simplify administration.

TEKLYNX CENTRAL offers the following features:

Label Design Security and Traceability – You can create all of your label templates in the label designer and secure them in the label database. All modifications and print requests are tracked in the database to provide an audit trail of print and label history.

Browser-Based Printing Interface – The browser-based printing interface uses a unique data input model that allows you to eliminate unnecessary user steps by limiting access to labels at the work order, workstation, and printer level. In addition, the configurable interface allows you to use terminology specific to your business environment, which reduces training time for new users.

Label Printing – Print requests that are sent from a host system or the browser-based user interface are processed and sent to networked printers.

Chapter 2-2 Installation Guide

Installing TEKLYNX CENTRAL

Insert the DVD, click TEKLYNX CENTRAL Installation, and then click the Install icon. If the DVD does not automatically launch, use the Windows Run command to type the letter of the DVD drive followed by index.hta (for example, D:\index.hta) and press ENTER.

The TEKLYNX CENTRAL Installer opens.




Figure 2-1 TEKLYNX CENTRAL Installer

2 Click Start. If a required Windows application is missing on your system, the installation program will prompt you to install the prerequisite file. Installation Chapter 2-3




Figure 2-2 Required Windows Prerequisite

Click Install to install any required prerequisites.

Installation of Windows prerequisites may require a system reboot to complete the installation. If a system reboot is required, a message will appear prompting you to restart your computer. Click **Yes** to restart your computer.

3 If all required Windows prerequisites are already installed, or after the installation of any necessary prerequisites has finished, the TEKLYNX CENTRAL Installation Wizard appears. Chapter 2-4 Installation Guide




Figure 2-3 TEKLYNX CENTRAL Installation Wizard

4 Click Next.

The License Agreement window appears.



Figure 2-4 License Agreement window

Installation Chapter 2-5

5 Read the license agreement. If you agree with the terms of the license agreement, select I accept the terms of the license agreement and click Next.

The **Customer Information** window appears.




Figure 2-5 Customer Information window

6 Enter your name and the name of your company and click **Next**.

Chapter 2-6 Installation Guide

The **Destination Folder** window appears.




Figure 2-6 Destination Folder window

- 7 The default installation folder is C:\Program Files\Teklynx. If you would like to change the installation folder, click Change and browse to the desired location. Click Next.
- 7.1 On the next screen it's possible to specify if Online Printing Interface should be installed. Select preferred option and Click Next.

Installation Chapter 2-7



The Web Site Selection window appears.

Figure 2-7 Web Site Selection window

8 From the drop-down list, select the IIS web site. The IIS web site is the site from which the TEKLYNX CENTRAL browser-based printing interface will launch on client workstations. Click Next.

Chapter 2-8 Installation Guide

TEKLYNX CENTRAL - InstallShield Wizard Virtual directory Virtual directory definition Please specify the settings for virtual directory of the web site: Name: TKCENTRAL InstallShield < Back Next > Cancel

The Virtual Directory window appears.

Figure 2-8 Virtual Directory window

- 9 Specify the virtual directory name for the TEKLYNX CENTRAL browser-based printing interface. The virtual directory is part of the path that displays in the browser address bar when a user launches the printing interface. Click Next.
- 9.1 Specify the virtual directory name for the TEKLYNX CENTRAL Administrative interface. The virtual directory is part of the path that displays in the browser address bar when a user launches the printing interface. Click Next.

Installation Chapter 2-9

The **Database Type** window appears.




Figure 2-9 Database Type window

10 Choose the database type that will be used. Click Next.

Chapter 2-10 Installation Guide

 If Microsoft SQL Server was selected, the Database Server window appears.




Figure 2-10 Database Server window

From the drop-down list, select the SQL database server. This is the server that stores your configuration data (including label data and the relationships between items and labels).

Note: SQL configurations with "named instances" require special installation. During TEKLYNX CENTRAL installation, the wizard may display several possible database servers; for example, (Local)/DB instance name or (Workstation name)/DB instance name. You must select an item that contains a workstation name to ensure a correct connection. Click **Next**.

Installation Chapter 2-11

 If Oracle was selected, the Datasource window appears.




Figure 2-11 Datasource window

Enter the database that will be used for the LABEL ARCHIVE Server, UMSS\MSGS, and TEKLYNX CENTRAL instances, along with the relevant user credentials. This is the server that stores your configuration data (including label data and the relationships between items and labels). Click **Next**.

Note: Oracle database support is only available in 32-bit operating systems. The Microsoft Server 2003 R2 32-bit operating system is not supported.

Chapter 2-12 Installation Guide

11 You are ready to install TEKLYNX CENTRAL.




Figure 2-12 Ready to Install window

- 12 Click Install to begin installing TEKLYNX CENTRAL. The installation wizard will indicate when installation is complete.
- 13 Click Finish to exit the wizard.
- 14 When installation is complete, click Close to exit the TEKLYNX CENTRAL Installer.

CHAPTER 3

Using the Command Center

Once TEKLYNX CENTRAL has been installed, it can be used to administer all components of your enterprise labeling solution.

The Command Center

The TEKLYNX CENTRAL Command Center provides access to all components of your enterprise labeling software.




Figure 3-1 TEKLYNX CENTRAL Command Center

Use the default user to log into TEKLYNX CENTRAL for the first time. The user name for this account is **administrator** and the password is **admin**.

Managing Software Maintenance Agreements

A TEKLYNX Software Maintenance Agreement (SMA) gives you access to the latest software updates and training manuals for your registered TEKLYNX products. Entering your SMA number into the Command Center gives you quick access to your registration and expiration information. The system will

Chapter 3-2 Installation Guide

also remind you when your SMA contract is up for renewal.

Entering SMA Information

To enter your SMA number in TEKLYNX CENTRAL:

1 Click the Enter SMA Number link in the Software Maintenance Agreement (SMA) section. The SMA window opens.



Figure 3-2 SMA window

- 2 Type your SMA number in the **Enter SMA Number** field.
- 3 Click OK.

TEKLYNX CENTRAL will query the TEKLYNX SMA Center to locate the expiration date of your maintenance agreement. If your system does not have an Internet connection, an error message will appear.




Figure 3-3 SMA error message

Managing Licenses

The Licenses section of the Command Center allows you to manage user licenses and roles.

Adding/ Configuring User Rights

To add or configure user rights:

The **UMSS-MSGS** window opens.

Click the Manage Users link in the Licenses section.





Figure 3-4 UMSS-MSGS window

2 In the file tree on the left, go to UMSS-MSGS Servers > UMSS > Users, and right-click to select New > User.

Chapter 3-4 Installation Guide



The **User Properties - New** window opens.

Figure 3-5 User Properties - New window

3 On the User tab, enter the user's first and last name in the appropriate fields.

Then, if:

- Using UMSS authentication, enter a user name and password, and confirm the password.
- Using Active Directory, select Windows from the Authentication drop-down list and click the Browse button to locate the appropriate user.
- **4** On the **Group Memberships** tab, select the user groups that the user should belong to.

The following user groups can be used:

 Administrators – This user group is used by the installed components of TEKLYNX CENTRAL and provides initial access to the application to set up other

- users. You must have at least one user in this user group. This user can then create the TEKLYNX CENTRAL Administrator in user group ACAdministrator.
- PrintUsers This user group should not be used.
 TEKLYNX CENTRAL print users should be added to
 the ACPrintUser group.
- ACAdministrator This group presents Administration applications: Command Center, TC Web Administration, UMSS-MSGS Admin console, LA Server Administration.
- ACDesignUsers This group presents label design application: CODESOFT.
- ACPrintUsers This group presents printing application.
 Web Printing Interface license will be consumed.
- ACReportUsers Generate audit and history reports.
 Consumed by LA Client Console and via CODESOFT.




Figure 3-6 User Properties - Group Memberships tab

5 Click **OK** to save your user and group settings.

Chapter 3-6 Installation Guide

Viewing Connected Users

To view connected users:

1 Click the View Connected Users link.

The **Users** window appears.




Figure 3-7 Users window

2 Expand each user group to display the connected users.

Adding Licenses

To activate or add licenses:

1 Click Add Licenses. The License Activation window appears.



Figure 3-8 License Activation window

2 Click **Upgrade software license** and follow the on-screen instructions to upgrade your license.

Chapter 3-8 Installation Guide

Using the Label Designer

The Label Designer section of the Command Center provides links to launch the label designer application, where you can design and test print labels.

The label designer is powered by CODESOFT. For more information on designing and test printing labels, refer to the CODESOFT User Guide. For more information on checking labels in and out of the label database, refer to the LABEL ARCHIVE User Guide.

To launch the label designer, click the **Design and Test Labels** link in the Label Designer section.

Using the Label Manager

The Label Manager section of the Command Center provides links to manage labels and define approval rules.

Note: When a new version of a label is checked into LABEL ARCHIVE, the printing interface will automatically use this version for any subsequent print requests.

The TEKLYNX CENTRAL label manager is powered by LABEL ARCHIVE. For more information on managing labels, refer to the LABEL ARCHIVE Administrator's Guide and LABEL ARCHIVE User Guide.

Managing Labels

- Click the Delete, Archive, or Reset Labels link in the Label Manager section. This will launch the LABEL ARCHIVE Server application.
- 2 To delete labels:
 - a In the LABEL ARCHIVE Server application, select Console Root > LABEL ARCHIVE Server Administration > Tasks > Delete documents and data from the Console Root tree in the left pane.
 - b On the **Filter** tab, choose the categories and types of labels to search for.
 - c On the **Documents** tab, choose the labels to delete and click **Delete**.

Note: This action will permanently delete labels from the label database.

3 To archive labels:

- a In the LABEL ARCHIVE Server application, select
 Console Root > LABEL ARCHIVE Server
 Administration > Tasks > Archiving from the Console
 Root tree in the left pane.
- b On the **Filter** tab, choose the categories and types of labels to search for.
- c On the **Documents** tab, choose the labels to archive.
- d On the **Archive Options** tab, browse to the folder where the archived database will be stored. Enter a name for the backup file and click **Save**.
 - If you want to delete the label(s) from the label database, select **Delete after archive** and click **Archive**.
- 4 To reset the label's check out state:
 - a In the LABEL ARCHIVE Server application, select Console Root > LABEL ARCHIVE Server Administration > Tasks > Reset documents > Checkout state from the Console Root tree in the left pane.
 - b Select the desired label and click Reset.

Managing Approval Rules

- 1 Click Configure Approval Rules. The LABEL ARCHIVE Client application will launch.
- 2 In the LABEL ARCHIVE Client application, select Console Root > LABEL ARCHIVE Client Administration > Approval rules from the Console Root tree in the left pane.
- 3 To create a new approval rule, click **New**.
- 4 Enter a name for the new rule in the **Name** field.
- 5 Select when the step should be processed in the State drop-down list.
- **6** Select whether the step applies to a single user or a user group in the **Handler** drop-down list.

Chapter 3-10 Installation Guide

7 Select the user or user group in the Parameter drop-down list.

- 8 If the step is mandatory, select Must Approve in the Type drop-down list.
- 9 Click Apply.

Using the Print Manager

The Print Manager section of the Command Center provides links to create maps, configure sentinels, and monitor sentinels.

The TEKLYNX CENTRAL print manager is powered by SENTINEL. For more information on managing sentinels, refer to the SENTINEL Administrator's Guide and SENTINEL User Guide.

Configuring Printing for Data Watches

Two sentinel watches (TCPrint and Preview) are automatically created for the browser-based printing interface during the installation. Printers must be configured for both of these watches.

To add or remove printers:

- 1 Click the Configure Data Watch link in the Print Manager section of the Command Center.
- 2 Select the Print sentinel and click **Properties**.
- 3 On the Process tab, select CODESOFT Printing. Click Settings to launch the CODESOFT Printing Plug-in properties, where you can add or remove printers and define default settings.
- 4 After you have configured the printer, click **OK**.

Creating Additional Data Watches

Additional sentinel watches are required if you are sending data to TEKLYNX CENTRAL at print time to trigger a print request.

To create a sentinel watch:

1 Click the Configure Data Watch link in the Print Manager section of the Command Center.

Note: Data watches install automatically for the web printing module.

- 2 Click File > New.
- **3** On the **General** tab, enter a name and group for the data watch. If you are sending data within a file, select the map you created for the file.
- 4 On the Input tab, select how the data input will be sent to TEKLYNX CENTRAL (that is, what will trigger the print request). If you are sending data within a file, click File Capture. Click Settings to define the folder where the file will be created to trigger the print request.
- 5 On the Process tab, select CODESOFT Printing. Click Settings to launch the CODESOFT Printing Plug-in properties, where you can add or remove printers and define default settings. On the Archiving tab of the CODESOFT Printing Plug-in properties, enter a user name and password for a print user in the PrintUser group.
- 6 Click OK.
- 7 Check the Enable option in the Manager window.

Managing Printing Status

To activate a sentinel watch or monitor status:

- 1 Click the View Printing Status link in the Print Manager section of the Command Center.
- 2 To activate a watch, select the watch and select Activate from the SENTINEL menu.
- 3 To monitor print status, select Information from the View menu. The Information window opens. Select the Log tab to view print status.

Creating Map

A map file is required if you are sending data within a file to TEKLYNX CENTRAL at print time to trigger a print request.

Chapter 3-12 Installation Guide

Because the necessary sentinels and map files are automatically created when TEKLYNX CENTRAL is installed, you will only need to create map files if you have a specific need.

To create a map file:

- 1 Create a sample of the data that will be sent to trigger the print job.
- 2 Click the Create Map link in the Print Manager section of the Command Center.
- 3 Click **File** > **New** and follow the instructions in the wizard to create a new map file.

Using the Printing Interface

The Printing Interface section of the Command Center provides links to configure and test the printing interface.

The TEKLYNX CENTRAL label manager is powered by the Printing Interface. For more information on configuring the printing interface, refer to the *TEKLYNX CENTRAL 4.5* Administration Site Help File.

Configuring the Printing Interface

To configure the printing interface:

1 Click the Configure Printing Interface link in the Printing Interface section of the Command Center.

The Printing Interface Configuration Log In Page opens.




Figure 3-9 Log In Page

2 Enter your credentials and click the Log In button. If the system is configured to use your Windows credentials, click the Windows Authentication check box, then click Log In. Chapter 3-14 Installation Guide

3 After logging in, you will see the **Options** window.

]	Work order The identifier that specifies which Product will print.	Y	Use Printer Aliases Alias instead of Printer name on the Printing Interface Web Site.
	Workstation Logic Determine Products and printers based on Workstation. Printer Logic	V	Automatic Site Log Off Web site logs you out automatically after period of time. Re-login is required to apply this option
V	User Logic User Logic		Automatically Determine Workstation Determine Workstation based on static IP or MAC address.
*	Determine links between users, Work orders, Products and printers Test Print	~	Clear Label Quantity Clear Label quantity field after the Label has been printed
-	The ability to print a test Label with a watermark. Reprint		Clear variables after print Clear variables after the Label has been print
_	The ability to reprint a previously printed Label. Infinite print		Use Windows Authetication by Default Use windows authentication by default on Login screen of Printing Interface
V	Forces continuous processing of the same file data until a new file is received. Allow Queued Print Requests		Windows Authentication password prompt Windows users must enter password in printing and admin screen
~	Allows deferred batch printing by adding labels to queue based on workstation/username	Def	ault datetime format: MM/dd/yyyy
	Common variables When one variable change - all variables in Product with the same name will change too.		Product Variable Variable to be populated with product value
V	Quantity of Label Allow user to set quantity of Label which will be printed.		Add
✓	Truncate Label path Allow users to hide the Label path in all locations where the Label name displays.		Manage connections

Figure 3-10 Options window

On this screen you can choose the different features of the interface that you would like to enable. The options chosen here will affect the windows under the **Data Configuration** tab. After selecting the desired options, click the **Save** button.

All other configuration of the interfaces is done through the **Data Configuration** tab. Simply hover over **Data Configuration**, then choose the appropriate configuration menu you would like to access.

The following sections offer additional detail on specific configuration options.

Defining Workstations

TEKLYNX CENTRAL allows you to define unique workstations which will use the Printing Interface. This allows you to configure specific field labels and logic per workstation – these configuration steps are detailed in later sections.

To define workstations:

- 1 Click the **Configure Printing Interface** link in the Printing Interface section of the Command Center.
- 2 Log in using your credentials.
- **3** Click on the **Data Configuration** tab at the top of the screen, then choose the **Workstations** link.

Workstations




Figure 3-11 Printing Interface – Data Configuration tab,
Workstations link

- 4 Add any necessary workstations either by clicking Browse and navigating to the workstation or by manually entering in the workstation name.
- 5 Click Add to store each workstation.

Chapter 3-16 Installation Guide

Changing Field Labels for Workstations

TEKLYNX CENTRAL allows you to define different field labels for each workstation on your network.

To define field labels:

- Click the Configure Printing Interface link in the Printing Interface section of the Command Center.
- 2 Log in using your credentials.
- **3** Click on the **Data Configuration** tab at the top of the screen, then choose the **Naming** link.

Naming




Figure 3-12 Printing Interface – Data Configuration tab, Naming link

4 In the Workstation drop-down list, select the workstation for which you want to modify the interface terminology. Enter the field name substitutions as needed and click Save to store the changes for that workstation. Repeat as needed for each workstation.

Associating Labels with a Product

In TEKLYNX CENTRAL, you can link labels to products to ensure print users are printing the correct labels for each print job.

To associate labels with a product:

- 1 Click the **Configure Printing Interface** link in the Printing Interface section of the Command Center.
- **2** Log in using your credentials.
- **3** Click on the **Data Configuration** tab at the top of the screen, then choose the **Products** link.

Products



Figure 3-13 Printing Interface – Data Configuration tab, Products link.

4 Enter the names of your products in the **Add Product** field, then click **Add**.

Chapter 3-18 Installation Guide

5 Once all of your Products have been added, click on the Data Configuration tab at the top of the screen, then choose the Labels link.




Figure 3-14 Printing Interface – Data Configuration tab, Labels link

6 Choose the desired Product you would like to add labels to from the Product name drop-down list. Add Label

Product Name:
Product 1

Select Label Category:

CODESOFT

Identity lab (version: 1)

Tokksynch

Name: Doris Samuelson
Address: Bull Rum Ranch

City: Aurora

State: CQ Zip 89022

7 Click Add Label. The Add Label window appears.

Figure 3-15 Printing Interface – Add Label window

Add Label

- 8 Click on the CODESOFT link in the Select Label Category box.
- 9 Select the desired label in the list.

Use the empty field above the **Label Name** drop-down list to search for labels. The search results automatically update as you type into this box and any label names that contain matching text appear in the list.

Note: Each label will appear only once in the list regardless of how many versions are stored in your system.

10 Click Add Label to associate the selected label with the Product. Chapter 3-20 Installation Guide

Once the label is added you can click on it to bring up its variable options. Configure as necessary to define the prompt, determine whether to show, show but not allow edits or hide the variable, set a default value, choose to revert to this default value after a print request is sent, and even set the order in which the variables will appear.

Adding a Quantity Field to the Printing Interface

A **Quantity** field can be added to the printing interface so that the print user can enter a quantity for each label loaded within the interface.

To add the **Quantity** field to the printing interface:

- 1 Click the Configure Printing Interface link in the Printing Interface section of the Command Center.
- 2 Log in using your credentials.
- 3 Click on the **Options** tab.
- 4 Select the **Quantity of Labels** check box to add the **Quantity** field to the printing interface.




Figure 3-16 Printing Interface – Options tab, Quantity of Labels check box

5 Click Save.

Allowing Infinite Print Requests

TEKLYNX CENTRAL can be configured to continually print the same label from a single print request, until a new print request is sent.

To force continuous processing of the same file data until a new file is received:

- Click the Configure Printing Interface link in the Printing Interface section of the Command Center.
- 2 Log in using your credentials.
- 3 Click on the Options tab.
- 4 Select the **Infinite Print** check box to force continuous processing until a new print request is sent.




Figure 3-17 Printing Interface – Options tab, Infinite Print check box

5 Click Save.

Chapter 3-22 Installation Guide

Defining Common Variable Entry Settings

If multiple labels are associated with a product and the same variable names are used across all labels, you can set up TEKLYNX CENTRAL so that a user only enters the information once to update each common variable.

To define common variable entry settings:

- 1 Click the Configure Printing Interface link in the Printing Interface section of the Command Center.
- 2 Log in using your credentials.
- 3 Click on the **Options** tab.
- **4** Select the **Common Variables** check box to update the variable on all labels for a product when the variable is modified in one label design.

✓	Allow Queued Print Requests Allows deferred batch printing by adding labels to queue based on workstation/username
	Common variables When one variable change - all variables in Product with the same name will change too.
✓	Quantity of Label Allow user to set quantity of Label which will be printed.

Figure 3-18 Printing Interface – Options tab, Common Variables check box

5 Click Save.

Truncating the Label Path in the Printing Interface

You can configure TEKLYNX CENTRAL so that only the label name is displayed instead of the entire storage path. This will help keep the directory in which the label is stored concealed from end users.

To truncate the label path in the printing interface:

- 1 Click the Configure Printing Interface link in the Printing Interface section of the Command Center.
- **2** Log in using your credentials.
- 3 Click on the Options tab.
- **4** Select the **Truncate Label Path** check box to display only the label name in the printing interface.
- 5 Click Save.

Chapter 3-24 Installation Guide

Displaying the Printer Alias in the Printing Interface

TEKLYNX CENTRAL can be configured to display only the printer alias, which is assigned by the administrator when a TEKLYNX printer driver is installed, in place of the driver name. If this option is disabled, the driver name is displayed.

To display the printer alias in the printing interface:

- 1 Click the Configure Printing Interface link in the Printing Interface section of the Command Center.
- **2** Log in using your credentials.
- 3 Click on the Options tab.
- 4 Select the Use Printer Alias check box to display the printer alias in the printing interface instead of the driver name.
- 5 Click Save.

Testing the Printing Interface

To test the printing interface:

- 1 Click the Launch Printing Interface link in the Printing Interface section of the Command Center.
- **2** Enter a user name and password for a user with print access from the ACPrintUser group.
- 3 Enter information based on your business process and click Print. When you click Print, any changes that you have made to the form variables are saved.

A message will appear stating that the print job has been successfully sent to the server.

Using the Printing Interface on a Mobile Device

The TEKLYNX CENTRAL printing interface can be accessed on mobile devices using Google Chrome and Internet Explorer.

To use the printing interface on a mobile device:

- 1 In browser on the mobile device, enter the local network path to the printing web page. This path is defined during TEKLYNX CENTRAL installation.
- **2** Enter a user name and password for a user with print access from the ACPrintUser group.
- 3 Enter information based on your business process and tap Print.

Using the Workstation Install Module

The Workstation Install section of the Command Center allows you to remotely install the label designer application on client workstations.

Chapter 3-26 Installation Guide

Installing Software on a Client Workstation

 Click the Install Label Designer on Remote Workstation link in the Workstation Install section of the Command Center.

The **TEKLYNX CENTRAL Remote Installation** window appears.




Figure 3-21 TEKLYNX CENTRAL Remote Installation window

2 Click Browse and locate the remote workstation. Select the client workstation in the list.

Note: The user who is attempting to install the application via TEKLYNX CENTRAL must be an administrator on the remote workstation for the installation to be successful.

3 Click **Install** to begin the installation.

Installing Client Applications from the DVD

You can also install the label designer and label manager applications directly from the TEKLYNX CENTRAL DVD.

- On the client workstation, insert the DVD and install the Label Designer Client application.
- 2 Install the Label Manager Client application from the DVD. During the installation process, you will be asked to select the LABEL ARCHIVE Server. Enter or select the name of the server on which TEKLYNX CENTRAL is installed.

3 Edit the CS.ini file, which is installed in C:\Documents and Settings\All Users\Application Data\Teklynx\CODESOFT. For Windows Vista and 2008 users, this file is located in C:\ProgramData\Teklynx\CODESOFT.

Add the line **UMSSAVAILABLE=1** in the General section of the file.

- **4** Launch CODESOFT. The application will launch in evaluation mode.
- 5 Go to Tools > Users Management. The Users Management window opens.




Figure 3-22 User Management window

- 6 Select the Use User Management System (UMSS) option.
- 7 In the server address tcp://localhost:8989, replace localhost with the name of the server on which TEKLYNX CENTRAL is installed.
- 8 Click OK.
- 9 You will be prompted for a user name and password. Use the user name and password of a TEKLYNX CENTRAL administrator.
- 10 Restart CODESOFT for the changes to take effect.



